

BOOKS & LETTERS E-READERS


Designed by Whistler Studios
Featuring the Books & Letters Collection by Whistler Studios
Instructions for Kindle, Nook and Ipad ereaders



**PATTERN
TESTED**

#1 - CASE WITH BAND

#2 - ENVELOPE



#3 - JOURNAL STYLE



Check www.windhamfabrics.com Free Project section to see if there are any pattern updates before you start your quilt

WINDHAM FABRICS

812 Jersey Ave ~ Jersey City, NJ 07310 ~ 201.659.0444 ~ FAX: 201.659.9719
www.windhamfabrics.com email: retail@windhamfabrics.com

BOOKS & LETTERS E-READERS

Designed by Whistler Studios
Featuring the Books & Letters Collection by Whistler Studios
Instructions for Kindle, Nook and Ipad ereaders



34236-X



34237-1



34237-2



34239-5



34238-2



34238-4



34241-2

The instructions are for the three different kinds of e-readers. Pick the size that works for you. the sewing instructions are the same just follow the color coding for each size when cutting. N = Nook / K = Kindle / Ipad

CASE #1 - CASE WITH BAND

Fat Quarter each Fabric A / 34238-2 Blue Scroll and Fabric B / 34239-5 Ivory Letters
1/8 yd 34236-X Multi Stacked Books
1/4 yd lightweight Fusible Interlining
1/4 yd Heavy Weight Fusible Pellon

Cutting Instructions:

Fabric A - Cut (1) piece for cover

N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Fabric B - Cut (3) piece for lining

N = 6 1/4" x 8 3/4" / K = 5 3/4" x 7 1/2" / Ipad = 8 3/4" x 10 1/2"

Fabric C - Cut (1) piece for band 4" x 15" strip across the fabric for All sizes

Heavy Weight Fusible Pellon - Cut (1) piece

N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Light Weight Fusible Interlining - Cut (2) pieces

N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Cut (1) piece 4" x 15" for All sizes

1/2 inch elastic - Cut 4 pieces 3 3/4" long for All sizes

Small piece of 1" wide Black Velcro cut 1 1/2" long for All sizes

BOOKS & LETTERS E-READERS

Page 2

Assembly Directions

Note: All seams are $\frac{1}{4}$ " wide

OUTSIDE

1. Fuse lightweight interlining to wrong side of Fabric A cover using manufacturer's recommended instructions. Set aside.

LINING

2. Fold one piece of Fabric B lining with wrong sides together. Place folded edge at top and make sure the letters are in the upright direction. Diagram 1
3. Place on second piece of Fabric B lining and line up open edge at the bottom and sides. Stitch $\frac{1}{8}$ " from edge on 3 sides to hold in place. Diagram 2
4. You have just finished the Left case lining.

DIAGRAM 1





DIAGRAM 2



5. Place 1 piece of elastic in top left corner of 3rd piece of Fabric B 2" from the corner in both directions. Pin and stitch $\frac{1}{8}$ " from the edge. Stitch back and forth several times to reinforce. Diagram 3

DIAGRAM 3





DIAGRAM 4




6. Repeat for the other 3 corners. You have just completed the right case lining. Diagram 4

BOOKS & LETTERS E-READERS

Page 3

7. Join left and right sides together and press seam open. Fuse lightweight interlining to wrong side. Diagram 5


DIAGRAM 5



BAND

8. Fuse light weight interlining to wrong side of Fabric C. Fold with right sides together and stitch all opening edges leaving a 2" opening on long side for turning. Diagram 6

DIAGRAM 6



9. Trim corners of excess seam allowance, turn and press. Slipstitch opening closed.
10. Place soft side of Velcro 1 1/2" from edge on one end of the strip. Stitch around all 4 sides.

Diagram 7

1 1/2"

DIAGRAM 7



11. Turn strip over and sew the other piece of the Velcro at the edge. Diagram 8

DIAGRAM 8



FINISHING

12. Fuse Heavy Weight Pellon to Fabric B lining following manufacturer's recommended instructions.
13. With right sides together place Fabric A on top of Fabric B. Stitch all around leaving a small 3" opening at the bottom so you can turn case to right side.
14. Trim corners and carefully trim seam allowance close to the seam on Pellon to reduce bulk when turning.
15. Turn the case to the right side; make sure corners are as square as possible.

BOOKS & LETTERS E-READERS


Page 4

16. Press flat. Slip stitch opening at bottom closed. Machine stitch 1/8" on all edges.

17. Center band on the outside of the case and place Velcro side that is 1 1/2" from edge on the left. Line up with edge of case. Pin in place. Diagram 9

Turn to inside of the case and stitch down the center on the center seam joining left and right sides of lining.

DIAGRAM 9



18. Add your personal ereader and Velcro the case closed. ENJOY!

CASE #2 - ENVELOPE

Fat Quarter Fabric A / 34237-2 Blue small books

Fat 1/8 each

Fabric B / 34237-1 Brown small brown books

Fabric C / 34238-4 Red scroll

Fabric D / 34238-2 Blue scroll

Fabric E / 34239-5 Ivory letters

1/4 light weight Fusible Interlining

1/4 yd Heavyweight Fusible Pellon

Cutting Instructions:

Cut squares for cover as follows:

Fabric C – Cut (6)

Fabric D – Cut (6)

Fabric E – Cut (4)

Fabric A – Cut (4)

Fabric B – Cut (4)

Fabric A – Cut (1) piece


N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Lightweight Fusible Interlining – Cut (1) piece

N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Heavyweight Fusible Pellon- Cut (1) piece


N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"



2 1/2" sq



2 1/8" sq



3 1/8" sq

BOOKS & LETTERS E-READERS

Page 5

Assembly Directions

All Seams are $\frac{1}{4}$ " wide


1. Assemble Squares as pictured and sew together with 6 squares across and 4 squares down. Diagram 1. As you sew the squares together, press the seams open to reduce bulk.

DIAGRAM 1



2. Once all squares are assembled, place on top fuse of the heavyweight Pellon and fuse following manufacturer's recommended instructions.
3. Fold with the right side together and machine stitch the side and bottom leaving the top edge open. Diagram 2

DIAGRAM 2



4. Fuse lightweight interlining to Fabric B lining on wrong side following manufacturer's recommended instructions.

BOOKS & LETTERS E-READERS

Page 6

5. With right sides together machine stitch down the side. Diagram 3
6. Press seam open and center it and then stitch the bottom closed. Diagram 4

DIAGRAM 3






DIAGRAM 4



7. Clip the seam allowance at the corners to reduce bulk.
8. Take the outside of the case and slide it into the lining with the right sides together. Stitch around the top edge leaving 2" open to turn the case. You may have to stretch the lining slightly to match the opening of the outside. (the inside is smaller to help reduce the amount of excess fabric when turned to the correct sides)
9. Turn the case to the right side out. Slip stitch the opening closed. Machine stitch the top edge with a 1/8" stitch to finish.

ENJOY!



BOOKS & LETTERS E-READERS

Page 7

CASE #3 - JOURNAL STYLE

Fat Quarter Fabric A / 34241-2 bargello and Fabric B / 34239-5 letters

1/4 yd lightweight Fusible Interlining

1/4 yd Heavy Weight Fusible Pellon

Cutting Instructions:

N = Nook / K = Kindle / Ipad

Fabric A - Cut (1) piece for outside cover

N = 12" x 8 3/4" / K = 11" x 7 1/2" / Ipad = 17" x 10 1/2"

Cut (1) piece for lining pocket

N = 6 1/4" x 8 3/4" / K = 5 3/4" x 7 1/2" / Ipad = 8 3/4" x 10 1/2"

Cut (3) 3" square for inside corners

Cut (2) 2 1/2" x 3 1/4" rectangles for tab closure for all sizes

Fabric B - Cut (2) pieces for lining

N = 6 1/4" x 8 3/4" / K = 5 3/4" x 7 1/2" / Ipad = 8 3/4" x 10 1/2"

Cut (1) 2" square letter of your choice for front cover for all sizes

Heavy Weight Pellon – cut (1) piece 12" x 8 3/4"

Fusible Interlining – Cut (2) pieces 12" x 8 3/4"

Cut (1) 2" square

1/4" elastic – cut (1) 4" long

Small piece of 1" wide Black Velcro cut 1 3/4" long

Scrap of Steam-A-Seam to appliqué letter to cover

Assembly Directions

Note: All seams are 1/4" wide

OUTSIDE

1. Take 2" square of your favorite letter and fuse to light weight interlining using manufacturer's suggested instructions.
2. Using Steam-A-Seam following manufacturer's recommended instructions, place square on cover 3" from top edge and 2" from right side. Appliqué with narrow zigzag stitch.
3. Machine stitch the soft side of the Velcro 3 1/8" from the top edge and 5/8" from the right side of cover.
4. Fuse lightweight interlining to wrong side of Fabric A (outside of case). Set aside.

BOOKS & LETTERS E-READERS

Page 8

LINING

5. Take one piece of Fabric A for lining pocket and fold with wrong sides together vertically. Diagram 1
6. Place folded Fabric A on one piece of Fabric B lining and line up the opening edge with left side of lining. Diagram 2
7. Stitch $\frac{1}{8}$ " from edge on 3 sides to hold in place. You have just finished the left inside lining.

DIAGRAM 1





DIAGRAM 2



8. Place 1 piece of elastic in top left corner of second piece Fabric B lining 2" from the corner in both directions. Pin and stitch $\frac{1}{8}$ " from the edge. Stitch back and forth several times to reinforce. Diagram 3





DIAGRAM 4




9. Fold the Fabric A 3" squares in half to form a triangle with wrong sides together. Place the triangle on the top right corner and edge stitch it in place. Repeat for the other 2 corners. You have just completed the right inside lining. Diagram 4

BOOKS & LETTERS E-READERS

Page 9

10. Join left and right sides together and press seam open. Diagram 5
11. With the wrong side on top of the heavyweight Pellon fuse together following manufacturer's recommended instructions.



12. Take (2) Fabric A rectangles for tabs and fold in half lengthwise. Carefully round of the corners on one end.
13. Separate the pieces and center the rough side of the Velcro about $\frac{3}{4}$ " from the rounded edge on one piece. Diagram 6
14. Fuse the other side of the tab with the lightweight fusible.
15. Sew the 2 pieces together leaving the square side open. Clip the seam allowance around the curved edge, turn and press flat. Edge stitch around the edges. Diagram 7




DIAGRAM 6




DIAGRAM 7

FINISHING

16. Place tab on lining 3" from the top edge on the right side with Velcro side down. Stitch at edge to hold in place. Diagram 8



DIAGRAM 8



BOOKS & LETTERS E-READERS

Page 10

17. With right sides together place Fabric A cover on top of Fabric B lining.
18. Stitch together leaving a small 3" opening at the bottom so you can turn case to right side.
19. Trim corners and carefully trim seam allowance close to the seam on Pellon to reduce bulk when turning.
20. Turn the case to the right side; make sure corners are as square as possible.
21. Press flat. Slip stitch opening at bottom closed. Machine stitch 1/8" on all edges.
22. Insert your personal ereader and ENJOY!



Be sure to visit www.windhamfabrics.com to see the complete collection
and to download other Free Projects